



# **PowerBuilder Compiler (PBC)**

## **User Guide**

Appeon® PowerBuilder® 2019

FOR WINDOWS

DOCUMENT ID: DC59772-01-1900-01

LAST REVISED: April 16, 2019

Copyright © 2019 Appeon. All rights reserved.

This publication pertains to Appeon software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Appeon Limited.

Appeon and other Appeon products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of Appeon Limited.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP and SAP affiliate company.

Java and all Java-based marks are trademarks or registered trademarks of Oracle and/or its affiliates in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Appeon Inc., 1/F, Shell Industrial Building, 12 Lee Chung Street, Chai Wan District, Hong Kong.

# Table of Contents

<b>1 What is PowerBuilder Compiler (PBC190.exe) .....</b>	<b>1</b>
1.1 System requirements .....	1
<b>2 Installing PBC190.exe .....</b>	<b>2</b>
<b>3 Compiling/Deploying PowerBuilder Projects Using PBC190.exe .....</b>	<b>3</b>
<b>4 PBC190.exe supported parameters .....</b>	<b>4</b>
4.1 c (and other compiling parameters) .....	4
4.2 d (and other deployment parameters) .....	4
4.3 h .....	8

# 1 What is PowerBuilder Compiler (PBC190.exe)

PowerBuilder Compiler (PBC190.exe hereinafter) is a standalone app that is used to compile or deploy PowerBuilder projects using DOS commands on Windows. It can be installed on any machine (either with or without a PowerBuilder installed). It is provided separately and is currently free for use.

Although there is no major difference between compilation using PBC190.exe and compilation (Run > Full Build/Incremental Build) in PowerBuilder IDE, there are minor differences between deployment using PBC190.exe and deployment in PowerBuilder IDE (Run > Deploy). Please see the following table for details.

Difference	PowerBuilder	PBC190.exe
Resource files	You can specify a separate resource file to associate with a specific .pbl file.	Only a general resource file for all PBLs is included.

## 1.1 System requirements

Make sure your operating system is one of the following supported systems before you install and run PowerBuilder Compiler.

- Windows 7 32- or 64-bit with SP1
- Windows 8.1 32- or 64-bit
- Windows 10 32- or 64-bit
- Windows Server 2008 32- or 64-bit with SP2
- Windows Server 2012 R2
- Windows Server 2016

## 2 Installing PBC190.exe

The PBC190.exe installer is provided alone and you need to install it separately.

1. Double click the PBC190.exe installer AutoCompile.exe.
2. Click Next on the welcome screen.
3. Click Browse to select the installation directory or use the default directory, and then click Next.
4. Click Install and wait until the installation is complete.
5. Click Finish to exit the wizard. You may need to restart your computer.

The PBC190.exe installer does not support upgrade installation.

## 3 Compiling/Deploying PowerBuilder Projects Using PBC190.exe

You can either compile or deploy PowerBuilder projects using PBC190.exe.

1. Prepare the PowerBuilder projects in PowerBuilder IDE. **Make sure the PBT file is not read-only.**
2. In the command window, type PBC190 and the supported parameters such as /d, etc.

For the PBC190.exe supported parameters, see PBC190.exe supported parameters.

**Note:** You can create and generate the command using the PBC runtime parameters for deployment in PowerBuilder IDE, and then copy and paste the command to the command window. In the PowerBuilder IDE, click New > Project > Application to create the command with PBC runtime parameters. You may refer to *Creating a project* and *Defining an executable application project* in *PowerBuilder Users Guide* for more details on creating and defining a project.

## 4 PBC190.exe supported parameters

PBC190.exe supports the following three categories of parameters:

- Parameters for compiling PowerBuilder projects.
- Parameters for deploying PowerBuilder projects.
- Parameter for displaying PBC190.exe help.

### 4.1 /c (and other compiling parameters)

/c is used to compile the PowerBuilder projects and then saves the changes into the related PBLs.

/c supports:

1. two file types: .pbw or .pbt (.pbl is not supported currently).
2. two compilation modes: /f for full compilation; and /i for incremental compilation. If not specified, full compilation will be used by default.

#### Examples:

This example compiles test11.pbw in full compilation mode:

```
pb190 /c test11.pbw
```

This example compiles test11.pbw in incremental compilation mode:

```
pb190 /c test11.pbw /i
```

### 4.2 /d (and other deployment parameters)

/d is used to deploy the PowerBuilder projects to EXE and DLL/PBD files. It supports two file types: .pbw or .pbt (.pbl is not supported currently). For example, pb190 /d test11.pbw.

It also supports the compilation modes (/f for full compilation and /i for incremental compilation) and the following optional parameters for deployments. For example, pb190 /d "test11.pbt" /o "test11.exe" /r "test11.pbr" /w n /f /m y /tr n /in n /op 0 /x 32 /bg y /p "PowerBuilder Enterprise Series" /cp "Appeon" /de "Appeon Product File" /cr "Contains licensed copyright material by Appeon" /v "1.0.0.1" /fv "1.0.0.1" /ge 1 /le 0 /ps n

Please see the following table for details about these parameters.

Parameters	Description
/o	Name of the application executable file to be created. All the other related files will be deployed to the same folder as the

	<p>exe file. For example: /o d:\fo\test11.exe. If not specified, the same name as the PBT file will be used.</p> <p>PowerBuilder IDE -&gt; Project Painter: Executable file name option</p>
/r	<p>Name of a PBR (PowerBuilder resource file) that will be used to build the executable file. For example, /r test11.pbr.</p> <p>PowerBuilder IDE -&gt; Project Painter: Resource file name option</p>
/x	<p>Whether the platform to run the exe file is 32-bit or 64-bit. Values are 32 (the default) and 64. For example, /x 32.</p> <p>32-bit exe file can only run with the 32-bit runtime files, and 64-bit exe file can only run with the 64-bit runtime files.</p> <p>PowerBuilder IDE -&gt; Project Painter: Platform option</p>
/cp	<p>Name of the company. Default value is "Appeon".</p> <p>If there's space in the company name, the name should be quoted, for example, /cp "Appeon SZ".</p> <p>PowerBuilder IDE -&gt; Project Painter: Company name option</p>
/p	<p>Name of the product. Default value is "PowerBuilder Enterprise Series".</p> <p>If there's space in the product name, the name should be quoted, for example, /p "PowerBuilder Enterprise Series".</p> <p>PowerBuilder IDE -&gt; Project Painter: Product name option</p>
/de	<p>Description of the product. Default value is "Appeon Product File".</p> <p>If there's space in the description, the description should be quoted, for example, /de "Appeon Product File".</p> <p>PowerBuilder IDE -&gt; Project Painter: Description option</p>
/cr	<p>Copyright statement of the product. Default value is "Contains licensed copyright material by Appeon Inc. and others. Use and distribution of Sybase copyright material and licensed material is governed by Appeon End-user License Agreement.".</p> <p>If there is space in the copyright description, the description should be quoted, for example, /cr "All rights reserved.".</p> <p>PowerBuilder IDE -&gt; Project Painter: Copyright option</p>
/v	<p>Version of the software. Default value is "1.0.0.1".</p> <p>PowerBuilder IDE -&gt; Project Painter: Product version option (Properties displayed for executable)</p>



/fv	<p>Version of the file. Default value is "1.0.0.1".</p> <p>PowerBuilder IDE -&gt; Project Painter: File version option (Properties displayed for executable)</p>
/vn	<p>Version of the software which consist of four integer values representing the major version number, minor version number, fix version number, and build number, with each value separated by a decimal point, for example "11.0.0.3012".</p> <p>PowerBuilder IDE -&gt; Project Painter: Product version option (Executable version used by installer)</p>
/fvn	<p>Version of the file which consists of four integer values representing the major version number, minor version number, fix version number, and build number, with each value separated by a decimal point, for example "11.0.0.3012".</p> <p>PowerBuilder IDE -&gt; Project Painter: File version option (Executable version used by installer)</p>
/w	<p>Whether to use the Windows classic style. Values are:</p> <ul style="list-style-type: none"> <li>● y – use the Windows classic style.</li> <li>● n – (the default) use the PowerBuilder style.</li> </ul> <p>PowerBuilder IDE -&gt; Project Painter: Windows classic style option</p>
/m	<p>Whether to generate machine code executables and dynamic libraries. Values are:</p> <ul style="list-style-type: none"> <li>● y – generate machine code.</li> <li>● n – (the default) generate pseudo code.</li> </ul> <p>PowerBuilder IDE -&gt; Project Painter: Pcode option and Machine code option</p>
/tr	<p>Whether to generate a trace file for troubleshooting or profiling your application when you run the executable file. Values are y and n (the default).</p> <p>This parameter takes effect only when machine code executable is generated.</p> <p>PowerBuilder IDE -&gt; Project Painter: Trace information option</p>
/in	<p>Whether to display context information (such as object, event, and script line number) for runtime errors. Values are y and n (the default).</p> <p>This parameter takes effect only when machine code executable is generated.</p>

	PowerBuilder IDE -> Project Painter: Error context information option
/op	<p>Optimization level. Values are:</p> <ul style="list-style-type: none"> <li>● 0 - (the default) Optimize for speed</li> <li>● 1 - Optimize for space</li> <li>● 2 - None</li> </ul> <p>This parameter takes effect only when machine code executable is generated.</p> <p>PowerBuilder IDE -&gt; Project Painter: Optimization option</p>
/bg	<p>Whether to enable any code that you placed in DEBUG symbol conditional compilation code blocks. Values are y (the default) and n.</p> <p>PowerBuilder IDE -&gt; Project Painter: Enable DEBUG symbol option</p>
/ge	<p>Whether to generate manifest. Values are:</p> <ul style="list-style-type: none"> <li>● 0- (the default) No manifest</li> <li>● 1- Embedded manifest</li> <li>● 2- External manifest</li> </ul> <p>PowerBuilder IDE -&gt; Project Painter: Generation options option</p>
/le	<p>Execution level of manifest. This parameter takes effect only when /ge is set to 1 or 2. Values are:</p> <ul style="list-style-type: none"> <li>● 0- (the default) As Invoker</li> <li>● 1- Highest Available</li> <li>● 2- Require Administrator</li> </ul> <p>PowerBuilder IDE -&gt; Project Painter: Execution level option</p>
/ps	<p>Whether to allow access to the protected system UI. Values are y and n (the default). This parameter takes effect only when /ge is set to 1 or 2.</p> <p>PowerBuilder IDE -&gt; Project Painter: Allow access to protected system UI option</p>
/pd	<p>Whether to generate the PBD/DLL file for a PBL. Values are:</p> <ul style="list-style-type: none"> <li>● y- (the default) to generate PBD/DLL file</li> <li>● n- not to generate PBD/DLL file</li> </ul> <p>PowerBuilder IDE -&gt; Project Painter: PBD option</p> <p>When there are more than one PBLs in an application, each PBL can have its own /pd value. For example, when there are three</p>

	<p>PBLs, /pd nnn indicates only EXE file is generated and no PBD/DLL file is generated; /pd yny indicates the first and the third PBLs will have PBD/DLL files generated; /pd n indicates the first PBL will not have PBD/DLL file generated, and the second and the third PBL will have PBD/DLL files generated because the default value is y.</p> <p>If you specify to generate the EXE file only without the PBD/DLL file, make sure to test that the EXE file can run correctly.</p>
--	---

### 4.3 /h

/h is used for displaying the help of PBC190.exe parameters.

**Example:** pbc190 /h